




VIEW-i **Elite Plus** connecting to iPhone APP

AVIC Imaging Inc.

iOS APP – Apple Store

Connection to Wi-Fi of View-I Elite Plus

- Search “viewi” at Apple store using iPhone and download it onto iPhone
- Go to Wi-Fi Settings and choose “View-I Elite_WiFi”
- Enter Password “1234567890” and touch “Join” button
This password can be changed by Network Setting of VIEW-i APP



iOS APP – Apple Store

Setting Menu

- WiFi Setting
- Live View
- SD card : Playback / Storing the video clip into iPhone
- Camera Settings



iOS APP – Apple Store

WiFi Setting

- Touch “WiFi Setting” button
- SSID : View-I Elite_WiFi
- Password : 1234567890
- Change Password : Enter the new password “xxxxxxx” and then touch “Reactive Network”



iOS APP – Apple Store

Live View

- Touch “Live View” button
- The Front Video footage displays on the screen
- Touch “Rear” button and then the Rear Video footage displays on the screen

<Note> Turn Bluetooth off in the smartphone before starting “Live View”




iOS APP – Apple Store

SD card

- Touch “SD card” button
- The video clips display on the screen
- Choose a video clip and playback it at touching “▶” button.
- When touching “⬇️” button, the video clip will be stored into iPhone

<Note> Turn Bluetooth off in the smartphone before starting “Playback” or “Download” the video clips.



iOS APP – Apple Store

Camera Settings

- Touch “Camera Settings” button
- Settings Menu displays on the screen
 - Record Quality/Video Quality/Record Brightness
 - G-Sensor Sensitivity : Default 2
 - TV output Mode : NTSC/PAL
 - Video Clip Time : 1min/3min/5min
 - Speed Limit : Mile/Km

